



KB Name	How to transfer a viewON project to another PC		
Type	KB		
Since revision	NA		
KB Number	KB-0019-0	Build	12
Mod date	17. Oct 2008		

How to transfer a viewON project to another PC

This document will help you transfer a viewON project from your PC to another PC.


1 On your PC

You'll find the viewON projects inside the directory "viewON Projects" of your "My Documents" folder. There you should find a directory for each viewON project you created on your PC.

Select the project you want to export and zip the file.

C:\Users*<CurrentUser>*\Documents\ViewOn Projects\.

<CurrentUser> is the name of the user currently logged on Windows.



Right-click on the folder, click on **Send To** and choose **Compressed (zipped) Folder**.

If you have created your own Symbols (or modified existing symbols), make sure you zip the **Symbols** folder as well. This is very important, otherwise the symbol will not be available on the other computer.



KB Name	How to transfer a viewON project to another PC		
Type	KB		
Since revision	NA		
KB Number	KB-0019-0	Build	12
Mod date	17. Oct 2008		

2 On another PC

Copy and unzip the zipped files into the “My Documents” folder under the “viewON Projects” directory:

C:\Users\

<CurrentUser> is the name of the user currently logged on Windows.

IMPORTANT



Bear in mind that viewON does not accept sub-folders in workspace. So make sure there is not a folder inside another folder. Besides, the name of the folder cannot be changed, otherwise, viewON will not find the project.

If you also need to import new or modified symbols, then copy and unzip the symbols in the **Symbols** directory of your viewON

C:\Users\

3 For old viewON versions

If you are running viewON version 2, then the viewON workspace is stored under directory:

C:\Program Files[x86]\viewON 2\workspace\